

Running containers on LUMI

Christian Schou Oxvig, updates by JV – LUMI User Support Team

Containers – bring your own user space

- When running containers, the kernel, drivers and hardware is still provided by the host (LUMI) but the user space (directory tree) changes
- Benefits of using containers:
 - Enhanced reproducibility: A fixed (read-only) user space for each computational experiment
 - o Have a fully self-contained software environment
 - ^o Pin all versions of the software packages used
 - ^o Version control software environments
 - Enhanced portability: Run your container on other systems as long as the system libraries are compatible
 - Makes the same environment work on all compute platforms from laptop to supercomputer
 - Makes it easier to share your software environment with others just share the container
 - **Easily test and trash**: Try a new container if it doesn't work just trash the container and start over again
 - Bonus: Your software environment is a single file (the container) on the Lustre shared filesystems, which is much less stressful to Lustre and more performant, making for a much nicer experience for everyone on LUMI.





users

— yşr

Running containers on LUMI



• On LUMI, you can run Singularity/Apptainer containers

- Singularity/Apptainer are HPC container runtimes that allow you to run unprivileged containers, i.e. no need for root or sudo
- Singularity/Apptainer is not Docker, but if you have an existing Docker container, you can run it using Singularity/Apptainer
- Main singularity commands:
 - Getting (pulling) a container from a container registry singularity pull my_container.sif docker://ubuntu:22.04
 - Opening a shell inside the container singularity shell my_container.sif
 - o Executing a command inside the container singularity exec my_container.sif python3 my_script.py
- Running containers on compute nodes
 - o Launch computation using srun srun <options> singularity exec my_container.sif python3 my_script.py

Bind mounting parts of the host file system (1)

- When running a container on LUMI, where is /project, /scratch, etc.?
- You may "inject" parts of the host (LUMI) file system into the container by bind mounting it

singularity exec --bind /project/<project ID> my containr.sif tree $-L\overline{1}$ /

your_lumj_username@uan03:~> singularity exec --bind /project/project_465001363 ubuntu_tree.sif tree -L 1 /

```
|-- bin -> usr/bin
l-- boot
|-- dev
-- environment -> .singularity.d/env/90-environment.sh
l-- etc
l-- home
-- lib -> usr/lib
|-- lib32 -> usr/lib32
-- lib64 -> usr/lib64
-- libx32 -> usr/libx32
∣-- media
l-- mnt
|-- opt
-- proc
-- project
-- root
|-- run
|-- sbin -> usr/sbin
|-- singularity -> .singularity.d/runscript
I-- srv
-- sys
-- tmp
|-- users
-- usr
```

-- var



— bin

— boot

— dev

— etc

flash

home

— lib

— image

— lib64

— local

– mpt

— opt

- pfs

– proc

— root

— run

— srv

— svs — tmp

— users

— yşr

- var

— sbin

— scratch

— selinux

— projappl

— crav



Bind mounting parts of the host file system (2)

You typically want to bind mount your project folders (/project, /scratch, /flash). A shortcut is: module use /project/project_465001363/modules/AI-20241126 module load singularity-userfilesystems

- You may need to bind mount some of the host libraries to fully exploit the hardware
 - On LUMI you need this to get optimal performance when using the Slingshot 11 interconnect
 - WARNING: Be careful when bind mounting libraries from the host system. You can easily end up in a broken state if mixing the container libraries with host libraries.

\$ module use /project/project_465001363/modules/AI-20241126 \$ module load singularity-userfilesystems \$ singularity exec ubuntu_tree.sif tree -L 1 / -- appl -- bin -> usr/bin -- boot -- dev -- environment -> .singularity.d/env/90-environment.sh -- etc -- flash -- home -- lib -> usr/lib |-- lib32 -> usr/lib32 -- lib64 -> usr/lib64 -- libx32 -> usr/libx32 -- media -- mnt -- opt |-- pfs -- proc |-- projappl |-- project -- root -- run |-- sbin -> usr/sbin I-- scratch -- singularity -> .singularity.d/runscript -- srv -- svs |-- tmp -- users -- usr -- var

The LUMI (FakeCPE) containers (1)

LUMI

Official LUMI containers available on LUMI under /appl/local/containers/sif-images :

• Application images:

o jax

o mpi4py

o PyTorch

- o Tensorflow + Horovod
- Base images:

 Lumi-rocm-rocm-X.Y.Z.sif: ROCm + aws-ofi-rccl + MI250X (gfx90a) MIOpen kernels + rccltest

- · Remember to copy these to your project folder
 - We may remove/replace the container under /appl/local/containers/sif-image at any time!
 - If you like EasyBuild and modules, we also provide a set of easyconfigs to "install" the containers.

vour lumi username@uan03:~> ls -1 /appl/local/containers/sif-images gcc.sif.sif lumi-jax-rocm-6.2.0-python-3.12-jax-0.4.28.sif lumi-mpi4py-rocm-6.2.0-python-3.12-mpi4py-3.1.6.sif lumi-pytorch-rocm-5.7.3-python-3.12-pytorch-v2.2.2.sif lumj-pytorch-rocm-6.0.3-python-3.12-pytorch-v2.3.1.sif lumi-pytorch-rocm-6.1.3-python-3.12-pytorch-v2.4.1.sif lumj-pytorch-rocm-6.2.0-python-3.10-pytorch-v2.3.0.sif lumi-pytorch-rocm-6.2.0-python-3.12-pytorch-20240801-vllm-c7a3a47.sif lumi-pytorch-rocm-6.2.1-python-3.12-pytorch-20240918-yllm-4075b35.sif lumi-rocm-rocm-5.7.3.sif lumi-rocm-rocm-6.0.3.sif lumi-rocm-rocm-6.1.3.sif lumj-rocm-rocm-6.2.0.sif lumi-rocm-rocm-6.2.1.sif lumi-rocm-rocm-6.2.2.sif lumi-tensorflow-rocm-6.2.0-python-3.10-tensorflow-2.16.1-horoyod-0.28.1.sif perfetto4rocm.sif.sif vour lumi username@uan03:~>

The LUMI (FakeCPE) containers (2)

LUMI

- These LUMI containers are built against the Cray Programming Environment (CPE) However, the CPE is NOT included in the container due to license restrictions
- To fully utilize the Slingshot 11 interconnect with these containers, you need to bind mount parts of the CPE when running the container singularity exec --bind /var/spool/slurmd,/opt/cray,/usr/lib64/libcxi.so.1, /usr/lib64/libjansson.so.4 <program>
 - ^o For the containers making use of MPI (mpi4py and Horovod), this is required
 - For all other containers it is optional. If you don't include it, RCCL internode communication falls back to using slower TCP/IP sockets

Shortcut to getting the binds right:

module use /project/project_465001363/modules/AI-20241126
module load singularity CPEbits

module load singularity-CPEbits

 For the LUMI application containers, you need to run \$WITH_CONDA in the container to activate the conda environment in which the application, e.g. PyTorch, is installed

Further reading

LUMI

- LUMI Docs running containers page: <u>https://docs.lumi-supercomputer.eu/runjobs/scheduled-jobs/container-jobs/</u>
- LUMI (EasyBuild) Software Library: <u>https://lumi-supercomputer.github.io/LUMI-EasyBuild-docs/</u>