

Containers – bring your own user space



- When running containers, the kernel, drivers and hardware is still provided by the host (LUMI) - but the user space (directory tree) changes
- Benefits of using containers:
 - Enhanced reproducibility: A fixed (read-only) user space for each computational experiment
 - Have a fully self-contained software environment
 - Pin all versions of the software packages used
 - Version control software environments
 - Enhanced portability: Run your container on other systems as long as the system libraries are compatible
 - Makes the same environment work on all compute platforms from laptop to supercomputer
 - Makes it easier to share your software environment with others just share the container
 - Easily test and trash: Try a new container if it doesn't work just trash the container and start over again
 - Bonus: Your software environment is a single file (the container) on the Lustre shared filesystems, which is much less stressful to Lustre and more performant, making for a much nicer experience for everyone on IUMI.



Running containers on LUMI



- On LUMI, you can run Singularity/Apptainer containers
 - o Singularity/Apptainer are HPC container runtimes that allow you to run unprivileged containers, i.e. no need for root or sudo
 - Singularity/Apptainer is not Docker, but if you have an existing Docker container, you can run it using Singularity/Apptainer
- Main singularity commands:
 - Getting (pulling) a container from a container registry singularity pull my container.sif docker://ubuntu:22.04
 - Opening a shell inside the container singularity shell my container.sif
 - Executing a command inside the container singularity exec my_container.sif python3 my_script.py
- Running containers on compute nodes
 - Launch computation using srun
 srun <options> singularity exec my_container.sif python3 my_script.py

Bind mounting parts of the host file system (1)



- When running a container on LUMI, where is /project, /scratch, etc.?
- You may "inject" parts of the host (LUMI) file system into the container by bind mounting it singularity exec --bind /project/<project_ID> my containr.sif tree -L 1 /

-- var

```
your lymj username@uan03:~> singularity exec --bind /project/project 465001363 ybuntu tree.sif tree -L 1 /
|-- bin -> usr/bin
 -- boot
 -- environment -> .singularity.d/eny/90-environment.sh
l-- home
 -- lib -> usr/lib
 -- lib32 -> usr/lib32
 -- lib64 -> usr/lib64
 -- libx32 -> usr/libx32
 -- media
 -- mnt
 -- opt
 -- proc
 -- project
 -- root
 -- run
 -- sbin -> usr/sbin
-- singularity -> .singularity.d/runscript
|-- srv
 -- sys
-- tmp
 -- users
-- usr
```

```
ubuntu container directory tree
LUMI directory tree
                                  |-- bin -> usr/bin
   appl -> /pfs/lustrep4/appl
                                  I-- boot
 — bin
                                  I-- dev
 boot
                                  I-- environment -> .singularitv.d/env/90-environment
  cray
                                  I-- etc
  dev
                                  I -- home
  etc
                                  |-- lib -> usr/lib
  flash
                                  |-- lib32 -> usr/lib32
  home
                                  I-- lib64 -> usr/lib64
  image
                                  |-- libx32 -> usr/libx32
  — lib
                                  |-- media
  lib64
                                  |-- mnt
  local
  — mnt
                                  l-- opt
                                  I-- proc
  — opt
                                   -- root
  pfs
                                    - run
  proc
                                  |-- sbin -> usr/sbin
 — projappl
                                  |-- singularity -> .singularity.d/runscript
  - project -> /projappl
                                  l-- srv
  root
                                  -- sys
 - run
                                  I-- tmp
  sbin
                                  -- users
  scratch
                                  -- usr
  selinux
                                  -- var
  - sry
 - sys
  - tmp
  users
 — uşr
  – var
```

Bind mounting parts of the host file system (2)



You typically want to bind mount your project folders (/project, /scratch, /flash). A shortcut is:

```
module use /appl/local/containers/ai-modules
module load singularity-AI-bindings
```

- You may need to bind mount some of the host libraries to fully exploit the hardware
 - On LUMI you need this to get optimal performance when using the Slingshot 11 interconnect
 - WARNING: Be careful when bind mounting libraries from the host system. You can easily end up in a broken state if mixing the container libraries with host libraries.

```
$ module use /appl/local/containers/ai-module
$ module load singularity-AI-bindings
 singularity exec ubuntu tree.sif tree -L 1 /
 -- appl
 -- bin -> usr/bin
 -- boot
 -- environment -> .singularitv.d/env/90-environment.sh
 -- etc
 -- flash
 -- home
 -- lib -> usr/lib
 -- lib32 -> usr/lib32
 -- lib64 -> usr/lib64
 -- libx32 -> usr/libx32
 -- media
 -- mnt
 -- opt
 -- pfs
 -- proc
 -- projappl
 -- project
 -- root
 -- run
 -- sbin -> usr/sbin
 -- scratch
 -- singularity -> .singularity.d/runscript
 -- srv
 -- SVS
 -- tmp
 -- users
 -- usr
 -- var
```

Official LUMI containers



Official LUMI containers available on LUMI under /appl/local/containers/sif-images:

- Application images:
 - o JAX
 - o mpi4py
 - PyTorch
 - Tensorflow + Horovod
- Base images:
 - Lumi-rocm-rocm-X.Y.Z.sif: ROCm + aws-ofi-rccl + MI250X (gfx90a) MIOpen kernels + rccltest
- Remember to copy these to your project folder
 - We may remove/replace the container under /appl/local/containers/sif-image at any time!
 - If you like EasyBuild and modules, we also provide a set of easyconfigs to "install" the containers.

```
your lumi username@uan03:~$ ls -1 /appl/local/containers/sif-images/
gcc.sif.sif
lumi-jax-rocm-6.2.0-python-3.12-jax-0.4.28.sif
lumi-mpi4py-rocm-6.2.0-python-3.12-mpi4py-3.1.6.sif
lumi-pytorch-rocm-5.7.3-python-3.12-pytorch-v2.2.2.sif
lumi-pytorch-rocm-6.0.3-python-3.12-pytorch-v2.3.1.sif
lumi-pytorch-rocm-6.1.3-python-3.12-pytorch-v2.4.1.sif
lumi-pytorch-rocm-6.2.0-python-3.10-pytorch-v2.3.0.sif
lumi-pytorch-rocm-6.2.0-python-3.12-pytorch-20240801-vllm-c7a3a47.sif
lumi-pytorch-rocm-6.2.1-python-3.12-pytorch-20240918-vllm-4075b35.sif
lumi-pytorch-rocm-6.2.3-python-3.12-pytorch-v2.5.1.sif
lumi-rocm-rocm-5.7.3.sif
lumi-rocm-rocm-6.0.3.sif
lumi-rocm-rocm-6.1.3.sif
lumi-rocm-rocm-6.2.0.sif
lumi-rocm-rocm-6.2.1.sif
lumi-rocm-rocm-6.2.2.sif
lumi-tensorflow-rocm-6.2.0-python-3.10-tensorflow-2.16.1-horovod-0.28.1.sif
perfetto4rocm.sif.sif
your lumi username@uan03:~$
```

Utilize Slingshot 11 interconnect



- These LUMI containers are built against the Cray Programming Environment (CPE)
 However, the CPE is NOT included in the container due to license restrictions
- To fully utilize the Slingshot 11 interconnect with these containers, you need to bind mount parts of the CPE when running the container

```
singularity exec --bind /var/spool/slurmd,/opt/cray,/usr/lib64/libcxi.so.1,
  /usr/lib64/libjansson.so.4 cpream>
```

- o For the containers making use of MPI (mpi4py and Horovod), this is required
- For all other containers it is optional. If you don't include it, RCCL internode communication falls back to using slower TCP/IP sockets
- Shortcut to getting the binds right:
 module use /appl/local/containers/ai-modules
 module load singularity-AI-bindings

For the LUMI application containers, you need to run \$WITH_CONDA in the container to activate the conda environment in which the application, e.g. PyTorch, is installed

Further reading



- LUMI Docs running containers page:
 https://docs.lumi-supercomputer.eu/runjobs/scheduled-jobs/container-jobs/
- LUMI (EasyBuild) Software Library: https://lumi-supercomputer.github.io/LUMI-EasyBuild-docs/